



***UPDATE YEAR, MAKE, MODEL (YMM)
FROM AN FTP SITE***

VAST Enterprise

The material in this document is applicable for ALL VAST Enterprise Retail versions and for ALL VAST Enterprise Multi-Store versions.

NOTE - Do not use this process if you are using **WRENCHHEAD CATALOGS**.

If you have any problems or questions about this installation, please contact **VAST SUPPORT** at **1-800-803-9762**.

<h2 style="text-align: center;">Table of Contents</h2>
--

INTRODUCTION..... 3
VAST MULTI-STORE USERS:.....3
UPDATING YOUR YMM INFORMATION 4

INTRODUCTION

The following document will walk you through how to update the Year, Make and Model information from an FTP site, allowing you to update your information as soon as it becomes available.

Aftersoft Network NA will continue to include the latest YMM updates on the VAST Enterprise installation CD for new releases or updates to the VAST Enterprise software.



VAST MULTI-STORE USERS:


This update should be run at the **OFFICE**. In order to send the **YMM** changes to the **SHOP** there must be a check mark placed in the **CREATE TEXT FILE** box which will **UPDATE** each of the stores.

NOTE: These instructions must be completed on the **SERVER ONLY**.


All computers must be **CLOSED** and out of **VAST** before beginning, and they must **REMAIN CLOSED** until the entire process is **COMPLETE**.

UPDATING YOUR YMM INFORMATION

1. Open **VAST MAINTENANCE** and click on the Index button  and then click on  button.
2. Click on the 'Year,Make,Model Update' icon. You will see a screen similar to the one shown below.



3. Click on the “**Download Update YMM.mdb file from FTP...**” button, as highlighted above. You will see the following screen appear.



4. If the information on this screen is already entered and **CORRECT**, please **SKIP TO STEP 5**.

If this is the **FIRST TIME YOU HAVE ENTERED THIS SCREEN**, most of the fields will be blank. You will need to enter the following information into the corresponding fields on this screen.


FTP Server: ftp://altftp.aftersoftna.com/

FTP User Name: YMMUser


FTP Password: YMMUser1

FTP Directory: UpdateYMM

5. When you have finished entering the information, click **SAVE** to save your changes. In the future you will **NOT NEED TO RE-ENTER THIS INFORMATION AGAIN** unless something has changed.
6. Then click **LOAD** to download the YMM.update file from the FTP site. While the file is downloading, you will see the message “**DOWNLOAD IN PROGRESS...**” appears next to the LOAD button.
7. When the download is complete, a message box will appear on your screen similar to the one shown below. Click **OK**.



8. You will be taken back to the Year, Make, Model update screen, and another message box will appear asking if you would like to update the Year, Make and Model screen, as shown below. Click **YES**.



9. An hourglass will appear while the system is updating the YMM table. When the update is finished, you will be returned to the **VAST MAINTENANCE MAIN MENU**. The update is now complete and you can close out of VAST Maintenance.